

# Linux 系统运维之 MySQL DBA

## 版权信息：


Copyright (c) 2010 Zhao Shundong. Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.2 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".

## 使用说明：

- 1.为保证本文的完整性和可用性，本文遵循 GFDL 协议。
- 2.可以在 <http://www.unixhot.com/pdf/mysql.pdf> 找到本文的最新版本。
- 3.本文仅供参考使用，不承担任何因文档错误而造成的任何损失。
- 4.有任何问题可以在 UnixHot 运维社区讨论交流。
- 5.由于时间仓促，有些章节还不够深入，敬请谅解，下个版本加强。
- 6.有相关问题或业务合作。请邮件至 [admin@unixhot.com](mailto:admin@unixhot.com)。

## 相关文档：

1. 《Linux 系统运维之系统架构》 <http://www.unixhot.com/pdf/cluster.pdf>
2. 《Linux 系统运维之系统管理》 <http://www.unixhot.com/pdf/admin.pdf>
3. 《Linux 系统运维之运维监控》 <http://www.unixhot.com/pdf/monitor.pdf>
4. 《Linux 系统运维之性能优化》 <http://www.unixhot.com/pdf/tuning.pdf>
5. 《Linux 系统运维之运维规范》 <http://www.unixhot.com/pdf/guifan.pdf>
6. 《Linux 系统运维之 MySQL DBA》 <http://www.unixhot.com/pdf/mysql.pdf>



## 修订历史记录

## 内容简介

本文通过八个章节，分别阐述了再生产环境中，作为一名运维工程师和 MySQL DBA，应该关注的 MySQL 相关的内容，包括安装时的优化，企业最常用的 MySQL Replication 和 MySQL Cluster 方面的内容。第 7 章和第 8 章阐述了 MySQL 性能相关的内容，如果去监控目前的性能状态，如果去调优以获得最佳的性能指标。在最后一章着重介绍了 MySQL 的备份与恢复，这也是运维工程师和 DBA 工作的重中之重。

## 前言 (Preface)

MySQL 目前已经是各大互联网网站的首选数据库，不仅仅是因为它的开源，更是它良好的性能和插件式的存储引擎，受到越来越多人的青睐。本文也是 Linux 运维系列，所以讲解的 MySQL 数据库技术偏管理一些，在一些大公司已经将 DBA 划分为管理 DBA 和开发 DBA，他们关注的焦点不同。不过没有做过数据库开发的 DBA 并不能称之为真正的 DBA，所以我并不是 DBA，但作为一名运维工程师或者架构师，数据库又是你不得不掌握并精通的一个技术了。

# 目录 (Contents)

## 第 1 章 MySQL 概述

- 1.1 MySQL 简介
- 1.2 MySQL 相关链接

## 第 2 章 MySQL 源码安装

- 2.1 解压并编译安装
- 2.2 安装参数介绍
- 2.3 常见用户和组
- 2.4 安装数据库
- 2.5 相应权限的修改
- 2.6 配置文件
- 2.7 启动数据库并初始化密码

## 第 3 章 MySQL Replication

- 3.1 MySQL Replication 概述
- 3.2 安装 MySQL Slave 数据库
- 3.3 在 MySQL Master 上的配置
- 3.4 在 MySQL Slave 上的配置
- 3.5 测试复制是否成功

## 第 4 章 MySQL Proxy

- 4.1 MySQL 读写分离简介
- 4.2 MySQL 环境部署
- 4.3 MySQL Proxy 配置
- 4.4 MySQL Proxy 启动
- 4.5 MySQL Proxy 测试

## 第 5 章 MySQL Cluster

5.1 MySQL Cluster 简介

5.2 MySQL Cluster 环境搭建

5.3 MySQL Cluster 测试

## 第 6 章 Heartbeat 和 DRBD 高可用

6.1 DRBD 介绍

# 第 1 章 MySQL 概述

## 1.1 MySQL 简介

MySQL 是最流行的开放源码 SQL 数据库管理系统，它是由 MySQL AB 公司开发、发布并支持的。它的插入式存储引擎可以让使用者根据实际应用使用不同的存储。

## 1.2 MySQL 相关链接

MySQL 官方网站：<http://www.mysql.com/>

MySQL 社区版本下载地址：<http://www.mysql.com/downloads/mysql/>

MySQL 中文文档：<http://dev.mysql.com/doc/refman/5.1/zh/index.html>

MySQL 实用文档：<http://www.unixhot.com/pdf/mysql.pdf>

## 第 2 章 MySQL 源码安装

MySQL 的安装方式有很多，源码安装可定制性比较强，你可以指定你要安装的文件位置，你需要编译的功能等等。

### 2.1 解压并编译安装

```
[root@MySQL-Master ~]# cd /usr/local/src
[root@MySQL-Master src]# wget
http://ftp.jaist.ac.jp/pub/mysql/Downloads/MySQL-5.1/mysql-5.1.56.tar.gz
[root@MySQL-Master src]# tar zxvf mysql-5.1.56.tar.gz
[root@MySQL-Master src]# cd mysql-5.1.56
[root@MySQL-Master mysql-5.1.56]# ./configure --prefix=/usr/local/mysql \
--localstatedir=/data/mysql --enable-assembler \
--with-client-ldflags=-all-static --with-mysqld-ldflags=-all-static \
--with-pthread --enable-static --with-big-tables --without-ndb-debug \
--with-charset=utf8 --with-extra-charsets=all \
--without-debug --enable-thread-safe-client --enable-local-infile --with-plugins=max
[root@MySQL-Master mysql-5.1.56]# make && make install
```

### 2.2 安装参数介绍

```
--prefix=/usr/local/mysql //主程序安装目录
--localstatedir=/data/mysql //数据文件存放目录
--with-client-ldflags=-all-static --with-mysqld-ldflags=-all-static//静态编译安装 mysql 客户端和服务端
--with-pthread //采用线程
--with-big-tables //对大表的支持
--with-charset=utf8 //默认字符集为 utf8
--with-extra-charsets=all //安装所有字符集
--without-debug //去掉 debug 模式
--enable-thread-safe-client //以线程方式编译客户端
```

--with-plugins=max //添加对 innodb 及 partition 的支持

--enable-local-infile //对 load data 的支持

## 2. 3 创建用户和组

```
[root@MySQL-Master mysql-5.1.56]# groupadd mysql
```

```
[root@MySQL-Master mysql-5.1.56]# useradd -s /sbin/nologin -M -g mysql mysql
```

## 2. 4 安装数据库

```
[root@MySQL-Master mysql-5.1.56]# cd /usr/local/mysql/
```

```
[root@MySQL-Master mysql]# mkdir -p /data/mysql
```

```
[root@MySQL-Master mysql]# bin/mysql_install_db --basedir=/usr/local/mysql/ --datadir=/data/mysql/  
--user=mysql
```

## 2. 5 相应权限的修改

```
[root@MySQL-Master mysql]# chown -R root:mysql /usr/local/mysql/
```

```
[root@MySQL-Master mysql]# chown -R mysql:mysql /data/mysql/
```

## 2. 6 配置文件

```
[root@MySQL-Master mysql]# cp /usr/local/mysql/share/mysql/my-medium.cnf /etc/my.cnf
```

```
[root@MySQL-Master mysql]# cp /usr/local/mysql/share/mysql/mysql.server /etc/init.d/mysqld
```

```
[root@MySQL-Master mysql]# chmod 755 /etc/init.d/mysqld
```

```
[root@MySQL-Master mysql]# chkconfig --add mysqld
```

```
[root@MySQL-Master mysql]# vim /root/.bash_profile
```

```
PATH=$PATH:$HOME/bin:/usr/local/mysql/bin
```

```
[root@MySQL-Master mysql]# source /root/.bash_profile
```

## 2. 7 启动数据库并初始化密码。

```
[root@MySQL-Master mysql]# service mysqld start
```

Starting MySQL

[ OK ]

[root@MySQL-Master mysql]# mysqladmin -u root password unixhot //设置成自己的密码

## 第 3 章 MySQL Replication

### 3.1 MySQL Replication 概述

MySQL Replication 俗称 MySQL AB 复制，主要是通过把主服务器上的二进制日志通过网络传到从服务器上，MySQL 会自己把二进制日志转换成相关的 DDL, DML, DCL 等语句！但这种复制不同于 MySQL 簇，它是单向异步的。目前 MySQL 复制在企业应用率非常高，已经成为系统工程师必备的技能。

具体的原理请参考 MySQL 官方文档：<http://dev.mysql.com/doc/refman/5.1/zh/index.html>

### 3.2 安装 MySQL Slave

实验环境：

实验环境是沿用第二章实验基础上的：

主机名	IP 地址	作用
MySQL-Master	192.168.0.13	MySQL 主库服务器
MySQL-Slave	192.168.0.14	MySQL 从库服务器

### 3.3 在 MySQL Master 上的配置

#### 3.3.1 创建 Replication 用户

[root@MySQL-Master ~]# mysql -u root -p

Enter password:

Welcome to the MySQL monitor. Commands end with ; or \g.

Your MySQL connection id is 2

Server version: 5.1.55-log Source distribution

Copyright (c) 2000, 2010, Oracle and/or its affiliates. All rights reserved.

This software comes with ABSOLUTELY NO WARRANTY. This is free software,  
and you are welcome to modify and redistribute it under the GPL v2 license

Type 'help,' or 'h' for help. Type '\c' to clear the current input statement.

```
mysql> GRANT REPLICATION SLAVE,reload,super ON *.* TO slave@192.168.0.14 IDENTIFIED BY  
'unixhot';
```

Query OK, 0 rows affected (0.00 sec)

Mysql>quit

### 3.3.2 修改 MySQL 配置文件。

```
[root@MySQL-Master ~]# vim /etc/my.cnf
```

```
server-id=1 #1..设置 server id  
log-bin=mysql-binlog #打开二进制日志，最好放在不同的硬盘上，减小磁盘 IO 消耗  
expire_logs_day=10 #设置二进制日志保存日期  
max_binlog_size=500M #设置每个 binlog 文件的大小
```

修改完后重新加载数据库： [root@MySQL-Master ~]# /etc/init.d/mysqld restart

注意： mysql-5.1.45.tar.gz 版本默认开启了 log-bin 选项，并且 server-id 默认为 1.

### 3.3.3 获得 Master DB 的相关信息

```
mysql> show master status;  
+-----+-----+-----+  
| File | Position | Binlog_Do_DB | Binlog_Ignore_DB |  
+-----+-----+-----+  
| mysql-bin.000003 | 106 | | |  
+-----+-----+-----+  
1 row in set (0.00 sec)
```

注意：供 Slave DB 连接时使用。

### 3.3.4 备份 Master DB 数据到 Slave DB

备份的方法有很多，可以直接复制数据文件，也可以使用 mysqldump，在这里不再详述。本文全新的搭建，所以不存在数据同步的问题。

## 3.4 在 MySQL Slave 上的配置。

### 3.4.1 修改 MySQL 配置文件

```
[root@MySQL-Slave ~]# vim /etc/my.cnf  
server-id=2 #配置多个从服务器时依次设置 id 号  
slave-skip-errors=all #mysql 复制可能出现主服务器上可以运行的语句，从服务器不能够运行，所以我们在 my.cnf 加一句 slave-skip-errors=all 意思是忽略所有的 sql 语句错误！  
relay-log=mysql-relay-bin #该文件用于存放 Slave 端的 I/O 线程从 Master 端读取的二进制文件信息
```

修改完后重启数据库： [root@MySQL-Slave ~]# /etc/init.d/mysql restart

### 3.4.2 在 Slave 服务器授权。

```
mysql> CHANGE MASTER TO
```

```
-> MASTER_HOST='192.168.0.13',
-> MASTER_USER='slave',
-> MASTER_PASSWORD='unixhot',
-> MASTER_LOG_FILE='mysql-bin.000003',
-> MASTER_LOG_POS=106;

Query OK, 0 rows affected (0.04 sec)
```

参数说明：

MASTER\_HOST: Master 主机名（或者 IP 地址）

MASTER\_USER: Slave 连接 Master 主机的用户名

MASTER\_PASSWORD: Slave 连接 Master 的用户密码

MASTER\_LOG\_FILE: 开始复制的日志文件名称

MASTER\_LOG\_POS: 开始复制的日志文件位置，也就是 Log Position。

### 3.4.3 启动 Slave DB

```
mysql> START SLAVE;
Query OK, 0 rows affected (0.00 sec)
```

## 3.5 测试复制是否成功。

可以在 Master DB 创建一个数据库，或者表，到 Slave DB 上看，如果配置成功就可以成功同步的。

MySQL Replication 的监控请参考《Linux 系统运维之监控》。

# 第 4 章 MySQL Proxy

## 4.1 MySQL 读写分离简介

MySQL-Proxy,是处在你的 MySQL 数据库客户和服务端之间的程序，它还支持嵌入性脚本语言 Lua。这个代理可以用来分析、监控和变换（transform）通信数据。

MySQL Proxy 最强大的一项功能是实现“读 写分离（Read/Write Splitting）”。基本的原理是让主数据库处理事务性查询，而从数据库处理 SELECT 查询。数据库复制被用来把事务性查询导致的变更同步到集群中的从数据库。



## 4.2 MySQL 环境部署

实验环境：

实验环境是沿用第三章实验基础上的：

主机名	IP 地址	作用
MySQL-Master	192.168.140.128	MySQL 主库服务器
MySQL-Slave	192.168.140.129	MySQL 从库服务器
MySQL-Proxy	192.168.140.130	MySQL 代理服务器

### 4.2.1 部署安装环境

```
[root@MySQL-Proxy ~]# rpm -q libevent glib2 pkgconfig libtool mysql-devel
[root@MySQL-Proxy ~]# cd /usr/local/src
[root@MySQL-Proxy src]# wget http://www.lua.org/ftp/lua-5.1.4.tar.gz
[root@MySQL-Proxy src]#
[root@MySQL-Proxy src]# wget http://gd.tuwien.ac.at/db/mysql/Downloads/MySQL-Proxy/mysql-proxy-0.6.0.tar.gz
[root@MySQL-Proxy src]# wget http://www.monkey.org/~provos/libevent-1.4.13-stable.tar.gz
```

#### 4.2.2 安装 lua

```
[root@MySQL-Proxy src]# tar zxvf lua-5.1.4.tar.gz
```

```
[root@MySQL-Proxy src]# cd lua-5.1.4
```

```
[root@MySQL-Proxy lua-5.1.4]# vi Makefile
```

修改：

```
INSTALL_TOP= /usr/local/lua
```

```
[root@MySQL-Proxy lua-5.1.4]# make && make linux && make install
```

```
[root@MySQL-Proxy lua-5.1.4]# export LUA_CFLAGS="-I/usr/local/lua/include"
```

```
LUA_LIBS="-L/usr/local/lua/lib -llua -ldl" LDFLAGS="-L/usr/local/libevent/lib -lm"
```

```
[root@MySQL-Proxy lua-5.1.4]# export CPPFLAGS="-I/usr/local/libevent/include"
```

```
[root@MySQL-Proxy lua-5.1.4]# export CFLAGS="-I/usr/local/libevent/include"
```

#### 4.2.3 安装 libevent

```
[root@MySQL-Proxy src]# tar zxvf libevent-1.4.13-stable.tar.gz
```

```
[root@MySQL-Proxy src]# cd libevent-1.4.13-stable
```

```
[root@MySQL-Proxy libevent-1.4.13-stable]# ./configure --prefix=/usr/local/libevent
```

```
[root@MySQL-Proxy libevent-1.4.13-stable]# make && make install
```

#### 4.2.4 安装 MySQL

```
[root@MySQL-Proxy src]# tar zxvf mysql-5.1.47.tar.gz
```

```
[root@MySQL-Proxy src]# cd mysql-5.1.47
```

```
[root@MySQL-Proxy mysql-5.1.47]# ./configure --prefix=/usr/local/mysql --without-server
```

#### 4.2.5 设置环境变量

```
[root@MySQL-Proxy src]# export LUA_CFLAGS="-I/usr/local/lua/include"
```

```
LUA_LIBS="-L/usr/local/lua/lib -llua -ldl" LDFLAGS="-L/usr/local/libevent/lib -lm"
```

```
[root@MySQL-Proxy src]# export CPPFLAGS="-I/usr/local/libevent/include"  
[root@MySQL-Proxy src]# export CFLAGS="-I/usr/local/libevent/include"
```

#### 4.2.6 安装 MySQL-Proxy

注意：如果你安装更高版本的 mysql-proxy 需要升级你的 glib。

```
[root@MySQL-Proxy src]# tar zxvf mysql-proxy-0.6.0.tar.gz  
[root@MySQL-Proxy src]# cd mysql-proxy-0.6.0  
[root@MySQL-Proxy mysql-proxy-0.6.0]# ./configure --prefix=/usr/local/mysql-proxy  
--with-mysql=/usr/local/mysql --with-lua  
[root@MySQL-Proxy mysql-proxy-0.6.0]# make && make install
```

### 4.3 MySQL-Proxy 配置

```
[root@MySQL-Proxy ~]# /usr/local/mysql-proxy/sbin/mysql-proxy --help-all
```

Usage:

```
mysql-proxy [OPTION...] - MySQL Proxy
```

Help Options:

- ?, --help
- help-all
- help-admin
- help-proxy

admin module

```
--admin-address=<host:port> #管理主机监听地址和端口， 默认是 4041
```

proxy-module

```
-proxy-address=<host:port> #代理主机监听地址和端口， 默认是 4040
```

```
--proxy-read-only-backend-addresses=<host:port> #只读连接时， 代理服务器的监听地址及端口。
```

默认 4042

```
--proxy-backend-addresses=<host:port>      #连接后端真实服务器时的地址及监听端口， 默认是 3306  
--proxy-skip-profiling  
--proxy-fix-bug-25371  
--proxy-lua-script=<file>          连接真实服务器的地址及监听端口， 默认是 3306  
--no-proxy
```

Application Options:

```
-V, --version  
--daemon  
--pid-file=<file>
```

## 4.4 MySQL Proxy 启动

### 4.4.1 命令行启动

```
[root@MySQL-Proxy ~]# /usr/local/mysql-proxy/sbin/mysql-proxy \  
> --proxy-read-only-backend-addresses=192.168.140.129:3306 \  
> --proxy-backend-addresses=192.168.140.128:3306 \  
> --proxy-lua-script=/usr/local/mysql-proxy/share/mysql-proxy/rw-splitting.lua &
```

检测是否开始监听：

```
[root@MySQL-Proxy ~]# netstat -ntlp | grep mysql  
tcp        0      0 0.0.0.0:4040          0.0.0.0:*      LISTEN      28739/mysql-proxy  
tcp        0      0 0.0.0.0:4041          0.0.0.0:*      LISTEN      28739/mysql-proxy
```

### 4.4.2 脚本启动

```
[root@MySQL-Proxy ~]# vi /etc/init.d/mysql-proxy  
#!/bin/bash  
PRODIR=/usr/local/mysql-proxy
```

```
LUA_PATH=$PRODIR/share/mysql-proxy
```

```
start() {
$PRODIR/sbin/mysql-proxy --proxy-read-only-backend-addresses=192.168.140.129:3306
--proxy-backend-addresses=192.168.140.128:3306 --proxy-lua-script=$LUA_PATH/rw-splitting.lua
>>$PRODIR/mysql-proxy.log &
```

```
}
```

```
stop() {
kill $(pidof mysql-proxy)
if [ $? -ne 0 ];then
    kill -9 $(pidof mysql-proxy)
fi
}
```

```
case "$1" in
    start)
        start
        ;;
    stop)
        stop
        ;;
    restart)
        stop
        start
        ;;
    *)
        echo $"Usage: $0 {start|stop|restart}"
        Esac
```

```
[root@MySQL-Proxy ~]# chmod +x /etc/init.d/mysql-proxy
```

```
[root@MySQL-Proxy ~]# /etc/init.d/mysql-proxy start
```

## 4.5 MySQL Proxy 测试

### 4.5.1 测试环境部署

在 MySQL-Master 上创建测试数据库和用户。

```
mysql> create database unixhot;  
mysql> GRANT ALL PRIVILEGES ON unixhot.* to proxytest@'%' identified by 'unixhot';
```

### 4.5.2 连接测试

```
[root@MySQL-Proxy ~]# mysql -h 192.168.140.130 -P 4040 -u proxytest -p
```

输入密码即可登录。


**注意：**在这里只做简单测试，具体请根据具体应用进行测试。由于目前 MySQL Proxy 技术还不够成熟，如果想在生产环境部署，请慎用。

## 第 5 章 MySQL Cluster

### 5.1 MySQL Cluster 简介

请参考官方文档：<http://dev.mysql.com/doc/refman/5.1/zh/ndbcluster.html>

下面是官方的 MySQL Cluster 的基本架构图：



## 5.2 MySQL Cluster 环境搭建

搭建 MySQL Cluster 至少需要三个节点，一个管理节点来实现管理功能，一个 SQL 节点主机来实现 MySQL server 功能，一个 ndb 节点主机实现 NDB Cluster 的功能。

### 5.2.1 实验环境

主机名	IP 地址	作用
MySQL-SQL-Node1	192.168.140.128	SQL 节点服务器
MySQL-Data-Node1	192.168.140.129	Data 节点服务器
MySQL-MGM-Node	192.168.140.130	管理节点服务器

注意：如果你的实验环境是根据本文的设置，为了对 MySQL Cluster 的配置不冲突，请整理前面的实验环境，如下：

```
[root@MySQL-Proxy ~]# /etc/init.d/mysql-proxy stop
[root@MySQL-Slave ~]# /etc/init.d/mysqld stop
[root@MySQL-Master ~]# /etc/init.d/mysqld stop
```

### 5.2.2 部署安装环境

```
[root@MySQL-SQL-Node1 src]# wget
http://ftp.jaist.ac.jp/pub/mysql/Downloads/MySQL-Cluster-7.1/mysql-cluster-gpl-7.1.3.tar.gz
[root@MySQL-SQL-Node1 src]# chmod +x mysql-cluster-gpl-7.1.3.tar.gz
[root@MySQL-SQL-Node1 src]# scp mysql-cluster-gpl-7.1.3.tar.gz 192.168.140.129:/usr/local/src
[root@MySQL-SQL-Node1 src]# scp mysql-cluster-gpl-7.1.3.tar.gz 192.168.140.130:/usr/local/src
```

### 5.2.3 部署管理(MGM)节点

#### 1> 安装 MGM 节点

```
[root@MySQL-MGM-Node ~]# cd /usr/local/src
[root@MySQL-MGM-Node src]# tar zxvf mysql-cluster-gpl-7.1.3.tar.gz
[root@MySQL-MGM-Node src]# cd mysql-cluster-gpl-7.1.3
[root@MySQL-MGM-Node mysql-cluster-gpl-7.1.3]# ./configure --prefix=/usr/local/mysqlcluster \
--with-charset=utf8 --with-collation=utf8_general_ci \
--with-client-ldflags=-all-static -with-mysqld-ldflags=-all-static \
--enable-assembler --with-extra-charsets=complex \
--enable-thread-safe-client --with-big-tables --with-readline \
--with-ssl --with-embedded-server --enable-local-infile \
--with-unix-socket-path=/usr/local/mysqlcluster/tmp/mysql.sock \
--sysconfdir=/usr/local/mysqlcluster/etc --without-debug \
--with-mysqld-user=mysql --with-plugins=max
```

```
[root@MySQL-MGM-Node mysql-cluster-gpl-7.1.3]# make && make install
```

## 2> 配置 MGM 节点

```
[root@MySQL-MGM-Node ~]# cd /usr/local/mysqlcluster/
```

```
[root@MySQL-MGM-Node mysqlcluster]# mkdir mysql-cluster
```

```
[root@MySQL-MGM-Node mysqlcluster]# vi mysql-cluster/config.ini
```

```
[NDBD DEFAULT]
```

```
NoOfReplicas= 1
```

```
DataMemory=50M
```

```
IndexMemory=10M
```

```
[NDB_MGMD]
```

```
id=1
```

```
HostName=192.168.140.130
```

```
DataDir=/usr/local/mysqlcluster/mysql-cluster
```

```
[NDBD]
```

```
id=2
```

```
HostName=192.168.140.129
```

```
DataDir=/usr/local/mysqlcluster/ndbdata
```

```
[mysqld]
```

```
id=3
```

```
HostName=192.168.140.128
```

## 3> 启动 MGM 节点

```
[root@MySQL-MGM-Node mysqlcluster]# libexec/ndb_mgmd -f  
/usr/local/mysqlcluster/mysql-cluster/config.ini
```

## 5.2.4 部署 NDBD 节点

### 1> 安装 NDBD 节点

```
[root@MySQL-Data-Node1 ~]# cd /usr/local/src
[root@MySQL-Data-Node1 src]# tar zxvf mysql-cluster-gpl-7.1.3.tar.gz
[root@MySQL-Data-Node1 src]# cd mysql-cluster-gpl-7.1.3
[root@MySQL-Data-Node1 mysql-cluster-gpl-7.1.3]# ./configure --prefix=/usr/local/mysqlcluster \
--with-charset=utf8 --with-collation=utf8_general_ci \
--with-client-ldflags=-all-static -with-mysqld-ldflags=-all-static \
--enable-assembler --with-extra-charsets=complex \
--enable-thread-safe-client --with-big-tables --with-readline \
--with-ssl --with-embedded-server --enable-local-infile \
--with-unix-socket-path=/usr/local/mysqlcluster/tmp/mysql.sock \
--sysconfdir=/usr/local/mysqlcluster/etc --without-debug \
--with-mysqld-user=mysql --with-plugins=max
[root@MySQL-Data-Node1 mysql-cluster-gpl-7.1.3]# make && make install
```

### 2> 配置 NDBD 节点

```
[root@MySQL-Data-Node1 ~]# cd /usr/local/mysqlcluster/
[root@MySQL-Data-Node1 mysqlcluster]# mkdir etc ndbdata
[root@MySQL-Data-Node1 mysqlcluster]# vi etc/my.cnf
[mysqld]
basedir=/usr/local/mysqlcluster/
datadir=/usr/local/mysqlcluster/var
user=mysql
```

```
port=3306
socket=/usr/local/mysql/tmp/mysql.sock
ndbcluster
ndb-connectstring=192.168.140.130
[mysql_cluster]
ndb-connectstring=192.168.140.130
```

### 3> 启动 NDBD 节点

```
[root@MySQL-Data-Node1 mysqlcluster]# libexec/ndbd --initial
```

注意：

第一次启动需要加--initial 参数进行初始化工作，在以后的启动中，千万不要加该参数，因为 ndbd 程序会清除之前建立的所有用于恢复的数据文件和日志文件。

### 5.2.5 部署 SQL 节点

#### 1> 安装 SQL 节点

```
[root@MySQL-SQL-Node1 ~]# cd /usr/local/src/
[root@MySQL-SQL-Node1 src]# tar zxvf mysql-cluster-gpl-7.1.3.tar.gz
[root@MySQL-SQL-Node1 src]# cd mysql-cluster-gpl-7.1.3
[root@MySQL-SQL-Node1 mysql-cluster-gpl-7.1.3]# ./configure --prefix=/usr/local/mysqlcluster \
--with-charset=utf8 --with-collation=utf8_general_ci \
--with-client-ldflags=-all-static -with-mysqld-ldflags=-all-static \
--enable-assembler --with-extra-charsets=complex \
--enable-thread-safe-client --with-big-tables --with-readline \
--with-ssl --with-embedded-server --enable-local-infile \
--with-unix-socket-path=/usr/local/mysqlcluster/tmp/mysql.sock \
```

```
--sysconfdir=/usr/local/mysqlcluster/etc --without-debug \
--with-mysqld-user=mysql --with-plugins=max
[root@MySQL-Data-Node1 mysql-cluster-gpl-7.1.3]# make && make install
```

## 2> 配置 SQL 节点

```
[root@MySQL-SQL-Node1 ~]# cd /usr/local/mysqlcluster/
[root@MySQL-SQL-Node1 mysqlcluster]# mkdir etc
[root@MySQL-SQL-Node1 mysqlcluster]# chown -R root:mysql .
[root@MySQL-SQL-Node1 mysqlcluster]# bin/mysql_install_db --user=mysql
[root@MySQL-SQL-Node1 mysqlcluster]# vi etc/my.cnf

[mysqld]
basedir=/usr/local/mysqlcluster/
datadir=/usr/local/mysqlcluster/var
user=mysql
port=3306
socket=/usr/local/mysql/tmpcluster/mysql.sock
ndbcluster
ndb-connectstring=192.168.140.130

[mysql_cluster]
ndb-connectstring=192.168.140.130
```

## 3> 启动 SQL 节点

```
[root@MySQL-SQL-Node1 mysqlcluster]# bin/mysqld_safe --user=mysql &
```

### 5.3 MySQL Cluster 测试

在管理节点上测试：

```
[root@MySQL-MGM-Node ~]# cd /usr/local/mysqlcluster/  
[root@MySQL-MGM-Node mysqlcluster]# bin/ndb_mgm  
-- NDB Cluster -- Management Client --  
ndb_mgm> show  
Connected to Management Server at: localhost:1186  
Cluster Configuration  
-----  
[ndbd(NDB)] 1 node(s)  
id=2 @192.168.140.129  (mysql-5.1.44 ndb-7.1.3, Nodegroup: 0, Master)  
  
[ndb_mgmd(MGM)] 1 node(s)  
id=1 @192.168.140.130  (mysql-5.1.44 ndb-7.1.3)  
  
[mysqld(API)] 1 node(s)  
id=3 @192.168.140.128  (mysql-5.1.44 ndb-7.1.3)
```

## 第 6 章 Heartbeat 和 DRBD 高可用

### 6.1 DRBD 介绍


DRBD(Distributed Replicated Block Device), DRBD 号称是 "网络 RAID", 开源软件, 由 LINBIT 公司开发。DRBD 分为两个部分, 内核中的驱动程序代码和用户空间的工具。Linux 2.6.33 之后的内核版本集成了 DRBD。

DRBD 实际上是一种块设备的实现, 主要被用于 Linux 平台下的高可用(HA)方案之中。他是有内

核模块和相关程序而组成，通过网络通信来同步镜像整个设备，有点类似于一个网络 RAID 的功能。也就是说当你将数据写入本地的 DRBD 设备上的文件系统时，数据会同时被发送到网络中的另外一台主机之上，并以完全相同的形式记录在一个文件系统中（实际上文件系统的创建也是由 DRBD 的同步来实现的）。本地节点（主机）与远程节点（主机）的数据可以保证实时的同步，并保证 IO 的一致性。所以当本地节点的主机出现故障时，远程节点的主机上还会保留有一份完全相同的数据，可以继续使用，以达到高可用的目的。



## 6.2 Heartbeat 介绍



## 6.3 部署前的准备工作

**第一步：**准备两台服务器，分别安装上 MySQL。

**第二步：**检查你的内核版本，如果是或高于 2.6.33 的话，就不需要安装了。

```
[root@MySQL-M ~]# uname -r
```

2.6.18-164.el5

**第三步：**准备 DRBD 使用的硬盘，我为两台服务器各加了一块硬盘。并分区，没有创建文件系统。

Device	Boot	Start	End	Blocks	Id	System
/dev/sdb1		1	261	2096451	83	Linux

**第四步：**IP 地址和主机名

主机名	IP 地址	作用
MySQL-node1	192.168.140.137	MySQL 主库服务器
MySQL-node2	192.168.140.139	MySQL 备库服务器

## 6.4 安装 DRBD

该小节所有内容需要在两个节点 MySQL-node1 和 MySQL-node2 分别执行。

### 6.4.1 下载软件包

```
[root@MySQL-node1 ~]# cd /usr/local/src
[root@MySQL-node1 src]# wget http://oss.linbit.com/drbd/8.3/drbd-8.3.7.tar.gz
[root@MySQL-node1 src]# tar zxvf drbd-8.3.7.tar.gz
[root@MySQL-node1 src]# cd drbd-8.3.7
```

### 6.4.2 编译为内核模块方式

```
[root@MySQL-node1 drbd-8.3.7]# ./configure --prefix=/usr/local/drbd \
> --sysconfdir=/etc --with-km
[root@MySQL-node1 drbd-8.3.7]# make
Module build was successful. (显示模块创建成功为正确)
[root@MySQL-node1 drbd-8.3.7]# make install
[root@MySQL-node1 ~]# whereis drbd
drbd: /etc/drbd.d /etc/drbd.conf /usr/local/drbd
```

### 6.4.3 载入 DRBD 模块到内核中

```
[root@MySQL-node1 ~]# modprobe drbd
[root@MySQL-node1 ~]# lsmod | grep drbd
drbd                  272504  0
[root@MySQL-node1 ~]# echo "modprobe drbd" >> /etc/rc.local
```

### 6.4.4 DRBD 命令

安装成功后，会发现，系统增加了以下三个命令：

```
[root@MySQL-node1 ~]# ls /sbin/drbd*
/sbin/drbdadm  /sbin/drbdmeta  /sbin/drbdsetup
```

## 6.5 DRBD 配置

### 6.5.1 /etc/drbd.conf

```
[root@MySQL-M ~]# cat /etc/drbd.conf
# You can find an example in /usr/share/doc/drbd.../drbd.conf.example
```

```
include "drbd.d/global_common.conf";
include "drbd.d/*.res";
```

默认情况下，该文件包含了/etc/drbd.d 目录下的配置文件，下面是我修改好的 drbd.conf

```
[root@MySQL-M ~]# cat /etc/drbd.conf
include "drbd.d/global_common.conf";
resource r0 { #定义一个资源名字 r0
    on MySQL-node1 {
        device /dev/drbd1; #设置一个DRBD device，编号是从 0 开始，主设备号 147。
        disk /dev/sdb1; #本地使用的device
        address 192.168.140.137:7789; #网络设置，IP 地址加端口
        meta-disk internal;
    }
    on MySQL-node2 {
        device /dev/drbd1;
        disk /dev/sdb1;
        address 192.168.140.139:7789;
        meta-disk internal;
    }
}
```

## 6.5 初始化设置

### 6.5.1 创建 DRBD 元数据

```
[root@MySQL-node1 ~]# drbdadm create-md r0
Writing meta data...
initializing activity log
NOT initialized bitmap
New drbd meta data block successfully created.

success

[root@MySQL-node1 ~]# drbdadm attach r0
[root@MySQL-node1 ~]# drbdadm syncer r0
[root@MySQL-node1 ~]# drbdadm connect r0

设置为主节点:

[root@MySQL-node1 ~]# drbdadm -- --overwrite-data-of-peer primary r0
[root@MySQL-node1 ~]# mkfs.ext3 /dev/drbd1
[root@MySQL-node1 ~]# cat /proc/drbd
version: 8.3.7 (api:88/proto:86-91)
GIT-hash: ea9e28dbff98e331a62bcbcc63a6135808fe2917 build by root@MySQL-M, 2010-11-26
02:36:34
```

```
1: cs:SyncSource ro:Primary/Secondary ds:UpToDate/Inconsistent C r---n
ns:75304 nr:0 dw:66388 dr:8952 al:25 bm:2 lo:0 pe:0 ua:0 ap:0 ep:1 wo:b oos:2024192
[>.....] sync'ed: 3.6% (2024192/2096348)K
finish: 1:52:27 speed: 256 (2,120) K/sec
```

```
[root@MySQL-node2 ~]# cat /proc/drbd
version: 8.3.7 (api:88/proto:86-91)
GIT-hash: ea9e28dbff98e331a62bcbcc63a6135808fe2917 build by root@MySQL-node2, 2010-11-27
01:50:08
```

```
1: cs:SyncTarget ro:Secondary/Primary ds:Inconsistent/UpToDate C r----
ns:0 nr:79880 dw:79880 dr:0 al:0 bm:2 lo:0 pe:0 ua:0 ap:0 ep:1 wo:b oos:2019616
```

```
[>.....] sync' ed: 3.8% (2019616/2096348)K  
finish: 0:42:04 speed: 512 (1,868) K/sec
```

## 第 7 章 MySQL 性能监控

MySQL 运行状态的监控是每个运维工程师，和 MySQL DBA 的主要工作之一。我们把 MySQL 的监控分为两个部分，一部分为基本状态的监控（请参考《Linux 系统运维之运维监控》），一部分为性能方面的监控，是为 MySQL 性能优化提供的参考信息，在这一章节，详细讲解，MySQL 性能监控方面的内容。

### 7.1 性能监控的工具

在 MySQL 的命令行中，DBA 们通常使用一下命令来获取 MySQL 的状态报告：

```
Mysql> show status;  
Mysql> show master status;  
Mysql> show slave status;  
Mysql> show innodb status;
```

下面是 show status 输出的最后一行，可以看到总共有 268 行。面对如此庞大的性能指标，让很多 DBA 望而生畏。

```
268 rows in set (0.00 sec)
```

### 7.2 mysqlreport

Mysqlreport 是用 perl 编写的一个命令行工具，解决了 show status 产生的大量我们难以阅读的状况。

## 7.2.1 mysqlreport 的相关资源

<http://hackmysql.com/mysqlreport> (官方首页)

<http://hackmysql.com/mysqlreportguide> (用户手册)

## 7.2.2 mysqlreport 安装

Mysqlreport 需要 Perl-DBI 和 Perl-DBD-Mysql 的支持。

```
[root@MySQL-Master ~]# cd /usr/local/src
[root@MySQL-Master src]# wget http://hackmysql.com/scripts/mysqlreport-3.5.tgz
[root@MySQL-Master src]# tar zxvf mysqlreport-3.5.tgz
mysqlreport-3.5/
mysqlreport-3.5/COPYING
mysqlreport-3.5/mysqlreportdoc.html
mysqlreport-3.5/mysqlreportguide.html
mysqlreport-3.5/mysqlreport
```

## 7.2.3 mysqlreport 参数详解

```
[root@MySQL-Master mysqlreport-3.5]# perl mysqlreport --help
mysqlreport v3.5 Apr 16 2008
mysqlreport makes an easy-to-read report of important MySQL status values.
```

Command line options (abbreviations work):

--user USER	Connect to MySQL as USER #用户名
--password PASS	Use PASS or prompt for MySQL user's password #密码
--host ADDRESS	Connect to MySQL at ADDRESS #主机 IP 或可以解析的域名
--port PORT	Connect to MySQL at PORT #mysql 端口。
--socket SOCKET	Connect to MySQL at SOCKET #设置通过 mysql socket 连接。

```
--no-my.cnf      Don't read ~/.my.cnf          #不读取 my.cnf 配置文件
--infile FILE    Read status values from FILE instead of MySQL
--outfile FILE   Write report to FILE        #输出写入到文件中
--email ADDRESS  Email report to ADDRESS (doesn't work on Windows) #发送输出日志到邮件
--flush-status   Issue FLUSH STATUS; after getting current values
--relative X     Generate relative reports. If X is an integer,
                  reports are live from the MySQL server X seconds apart.
                  If X is a list of infilenames (file1 file2 etc.),
                  reports are generated from the infilenames in the order
                  that they are given.
--report-count N Collect N number of live relative reports (default 1)
--detach         Fork and detach from terminal (run in background)
--help           Prints this    #打印此帮助日志
--debug          Print debugging information
```

Visit <http://hackmysql.com/mysqlreport> for more information.

## 第 8 章 MySQL 性能优化

MySQL 性能优化，是我们在进行应用系统优化时最后要考虑的问题，也是必需要考虑的问题，虽然每个应用的数据库都不尽相同，但还是有一些通用的优化方法，在这一章节主要讲解，我们常用的一些优化的方法。

### 8.1 索引缓存 (MYISAM)

索引是 MySQL 性能优化中一个重量级的角色，至于如何有效使用索引，大家可以询问开发人员或者参考其它的书籍，在这里主要讲讲索引缓存。

那么是不是所有的数据库都需要开启索引缓存呢，答案是否定的，我们需要参考的是您的应用，通常情况下，你的应用 Select 查询占数据库操作的 80%都需要使用缓存索引，而如果你的 Update 和 insert 比较多的话，使用索引缓存反而影响了 MySQL 的性能，可以说索引缓存是把双刃剑。

MySQL 使用 key\_buffer 选项来配置给索引缓存分配的内存空间大小。这个值需要你根据 mysqlreport 中的 Key 的使用和命中信息来决定大小。一般需要大于，你数据库中所有 MYI 文件的总大小。以下命令可以统计出所有 MYI 文件的总大小，结果的单位是字节。

```
ls -l | grep 'MYI$' | awk -F ' ' '{print$5}' | awk -v sum=0 '{sum += $NF} END{print sum}'
```

## 8.2 查询缓存(MYISAM、INNODB)

MySQL 支持查询缓存，它会在内存中开辟一块内存区用来缓存 select 查询的结果。对于 select 比较多的应用，应该开启查询缓存。同上，如果对于 select 和 update 几乎一样的应用，不推荐使用查询缓存，因为只要是缓存都存在缓存的过期重建，而每次 update 都会导致 update 的操作表的缓存被重建。

默认 MySQL 是没有使用查询缓存。在 my.cnf 添加以下内容开启：

```
Query_cahce_size = 200000000  
Query_cache_type =1  
Query_cache_limit = 1000000
```

## 8.3 线程缓存

MySQL 使用多线程来处理并发的链接，最大的线程数量通过 max\_connections 来制定，为了减少创建线程的重复开销，可以开启线程的缓存，其实就是开启线程的复用技术。

MySQL 默认是没有使用，在 my.cnf 添加以下内容开启：

```
Thread_cahce_size = 200
```

## 8.4 表高速缓存

表高速缓存是指 MySQL 访问一个表时，会判断表高速缓存是否有空间，如果有的话，就把表放入高速缓存中，再打开表，这样可以更快的访问表的内容。

通过 table\_cache 选项来设置大小。

MySQL 优化的路还很长，需要不断增加对 MySQL 的了解，对应用系统的了解，才能根据应用将 MySQL 的性能发挥到极致。笔者经验有限，本文档会持续更新，分享工作中的问题和经验，欢迎大家加入“运维社区”，请用 Google 搜索“运维社区”，我们始终站在第一位。

## 附录：GFDL 协议

(注：可以参考本协议的中文翻译版本 <http://www.thebigfly.com/gnu/FDLv1.3/>)

### GNU Free Documentation License

Version 1.3, 3 November 2008

Copyright © 2000, 2001, 2002, 2007, 2008 Free Software Foundation, Inc. <<http://fsf.org/>>

Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

#### 0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document "free" in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or noncommercially. Secondly, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of "copyleft", which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License in order to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

#### 1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein.

The "Document", below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as "you". You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A "Modified Version" of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A "Secondary Section" is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document's overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The "Invariant Sections" are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The "Cover Texts" are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A "Transparent" copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not "Transparent" is called "Opaque".

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image

formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The "Title Page" means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, "Title Page" means the text near the most prominent appearance of the work's title, preceding the beginning of the body of the text.

The "publisher" means any person or entity that distributes copies of the Document to the public.

A section "Entitled XYZ" means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as "Acknowledgements", "Dedications", "Endorsements", or "History".) To "Preserve the Title" of such a section when you modify the Document means that it remains a section "Entitled XYZ" according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

## 2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

## 3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document's license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

#### 4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version

gives permission.

- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.
- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H. Include an unaltered copy of this License.
- I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its Title Page, then add an item describing the Modified Version as stated in the previous sentence.
- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the "History" section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- K. For any section Entitled "Acknowledgements" or "Dedications", Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section Entitled "Endorsements". Such a section may not be included in the

Modified Version.

- N. Do not retitle any existing section to be Entitled "Endorsements" or to conflict in title with any Invariant Section.
- O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version's license notice. These titles must be distinct from any other section titles.

You may add a section Entitled "Endorsements", provided it contains nothing but endorsements of your Modified Version by various parties—for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

## 5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same

adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled "History" in the various original documents, forming one section Entitled "History"; likewise combine any sections Entitled "Acknowledgements", and any sections Entitled "Dedications". You must delete all sections Entitled "Endorsements".

## 6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

## 7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an "aggregate" if the copyright resulting from the compilation is not used to limit the legal rights of the compilation's users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document's Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

## 8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their

copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled "Acknowledgements", "Dedications", or "History", the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

## 9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense, or distribute it is void, and will automatically terminate your rights under this License.

However, if you cease all violation of this License, then your license from a particular copyright holder is reinstated (a) provisionally, unless and until the copyright holder explicitly and finally terminates your license, and (b) permanently, if the copyright holder fails to notify you of the violation by some reasonable means prior to 60 days after the cessation.

Moreover, your license from a particular copyright holder is reinstated permanently if the copyright holder notifies you of the violation by some reasonable means, this is the first time you have received notice of violation of this License (for any work) from that copyright holder, and you cure the violation prior to 30 days after your receipt of the notice.

Termination of your rights under this section does not terminate the licenses of parties who have received copies or rights from you under this License. If your rights have been terminated and not permanently reinstated, receipt of a copy of some or all of the same material does not give you any rights to use it.

## 10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See <http://www.gnu.org/copyleft/>.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License "or any later version" applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation. If the Document specifies that a proxy can decide which future versions of this License can be used, that proxy's public statement of acceptance of a version permanently authorizes you to choose that version for the Document.

## 11. RELICENSING

"Massive Multiauthor Collaboration Site" (or "MMC Site") means any World Wide Web server that publishes copyrightable works and also provides prominent facilities for anybody to edit those works. A public wiki that anybody can edit is an example of such a server. A "Massive Multiauthor Collaboration" (or "MMC") contained in the site means any set of copyrightable works thus published on the MMC site.

"CC-BY-SA" means the Creative Commons Attribution-Share Alike 3.0 license published by Creative Commons Corporation, a not-for-profit corporation with a principal place of business in San Francisco, California, as well as future copyleft versions of that license published by that same organization.

"Incorporate" means to publish or republish a Document, in whole or in part, as part of another Document. An MMC is "eligible for relicensing" if it is licensed under this License, and if all works that were first published under this License somewhere other than this MMC, and subsequently incorporated in whole or in part into the MMC, (1) had no cover texts or invariant sections, and (2) were thus incorporated prior to November 1, 2008.

The operator of an MMC Site may republish an MMC contained in the site under CC-BY-SA on the same site at any time before August 1, 2009, provided the MMC is eligible for relicensing.

## ADDENDUM: How to use this License for your documents

To use this License in a document you have written, include a copy of the License in the document and put the following copyright and license notices just after the title page:

Copyright (C) YEAR YOUR NAME.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled "GNU Free Documentation License".

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the "with ... Texts." line with this:

with the Invariant Sections being LIST THEIR TITLES, with the Front-Cover Texts being LIST, and with the Back-Cover Texts being LIST.

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.